


User and Smartcard Registration

With WinSig, CEFMS must know the IP address of the PC that a user is using. Registering a smartcard is accomplished by simply inserting your smartcard into the smartcard reader.

NOTHING WILL PROMPT YOU TO DO THIS!




When the smartcard is inserted into the card reader a window will appear announcing that the smartcard is being registered *(see below)*.




The following steps will help you register your card

- If this is a NEW card
- You are registering your card for the first time
- Or receive a message that states that your card must be re-registered

Step 1



(Front Side)



(Reverse Side)

Verify the Serial Number on the reverse side of your Smartcard and then Insert it into the Card reader attached to your PC.

Now you will see a windows like the following one.

Step 2

New smartcard registration

You are using a smartcard that has not yet been registered with the electronic signature system. Please fill out the information below, and click the "Register" button to complete, or click "Cancel" to register some other time.

Smartcard serial number: 00005158

Your Unix host logon ID (like u4rmfxyz):

Register

Cancel

At this time type your
USERID (M2XXXXXX).
This is a one time requirement.

**1st Check this number. Does it Match the
one on the reverse side of YOUR CARD?
Yes, then continue, but if is not then Stop
and Check with Barbara Wilkes.**

Click Register

Step 3

Are you sure?

Are you **ABSOLUTELY** sure you want to use the
Unix ID "M2RMBAAS" with smartcard
#00005158? Mistakes in smartcard registration
are **VERY** difficult to remedy.


If the above information
is **ABSOLUTELY** correct,
click here.

If the above information
is **NOT ABSOLUTELY**
correct, click here.

WinSig Configuration without a signature card


If you are using someone else 's *PC and do not have your signature card*, the following steps will help you
Configure WinSig

Step 1



**Click here for
WinSig Registration
(Located on the Desk Top).**

Step 2



A screenshot of a Windows-style dialog box titled "WinSig manual registration". The dialog has a blue title bar with a small icon on the left and standard minimize, maximize, and close buttons on the right. The main area is light gray and contains three text input fields. The first field is labeled "Primary KTC:" and contains the text "tk4.usace.army.mil". The second field is labeled "Secondary KTC:" and contains "tk3.usace.army.mil". The third field is labeled "CEAP logon ID (like u4rmfxyz):" and contains "M2IMCJG9". Below these fields is a checkbox labeled "Set this entry permanently", which is currently unchecked. At the bottom of the dialog are two buttons: "Exit" on the left and "Register" on the right.

WinSig manual registration

Primary KTC: tk4.usace.army.mil

Secondary KTC: tk3.usace.army.mil

CEAP logon ID (like u4rmfxyz): M2IMCJG9

☐ Set this entry permanently

Exit Register

1st Type User
CEFMS Login
ID

2nd Click for
Registration

3rd Click to Exit
and Save

REMEMBER

Any time a user's IP (Internet Protocol) address changes, that user needs to re-register to WinSig, either by inserting his/her smartcard (those with PC card readers) or clicking on the Manual Registration ICON on the desktop. Failure by a user to re-register upon an IP address change will cause WinSig to work improperly. Again, *For Users with Smartcards, it is recommended that you get into the practice of Always inserting your smartcard before enter CEFMS to prevent problems.*

**FOR ALL SMARTCARD USERS,
RECOMMEND THAT YOU GET INTO THE
PRACTICE
OF ALWAYS INSERTING YOUR
SMARTCARD BEFORE
YOU ENTER CEFMS,
TO PREVENT PROBLEMS.**

NEW LOGIN TO CEFMS WILL BE...

[cpc25: /swd/m2xxxxxx]%fms

**for other databases on our machine (CPC25)
(% fms m0)**